

Bluetooth BLE Integration in React Native Expo (New Architecture, iOS & Android).

Table of contents

By Chinweike Chinonso Michael

7 min. read · [View original](#)

Press enter or click to view image in full size



**Bluetooth (BLE)
in React Native
+ Expo**

Table of contents

Welcome to my space

If you've ever thought *"How do I get my React Native app talking to Bluetooth devices without losing my sanity?"* — then this article is for you.

The goal here is simple: to walk you through a step-by-step guide on how to integrate Bluetooth Low Energy (BLE) into your **React Native** project using the **new architecture** (yes, both iOS and Android included 🎉).

And hey — I've been in your shoes. Sharing this to make it easier for devs who just want a clear and working Bluetooth setup, without the doc-hunting.

Full source code:

<https://github.com/cmcWebCode40/React-Native-Expo-Bluetooth-Integration>

Bluetooth Classic vs Bluetooth Low Energy (BLE)

Before we dive into the juicy stuff, let's quickly clear up the difference between Bluetooth Classic and BLE:

In this guide, we'll focus **solely on BLE** — scanning, connecting, and exchanging data (READ/WRITE).

We'll be using the [react-native-ble-manager](#) package. It supports both the old and new architectures, but a few tweaks are required to make it work smoothly in an **Expo + React Native** project.

Project setup using Expo

```
npx create-expo-app@latest
```

Install the react-native-ble-manager library

You can as well use this package in your react native expo project.

Install the react native react-native-ble-manager library

```
npx expo install react-native-ble-manager
```

In your app.json file extend the plugin config to enable the package work.

```
"plugins": [  
  "expo-router",  
  [  
    "react-native-ble-manager",  
    {  
      "isBleRequired": true,  
      "neverForLocation": true,  
      "companionDeviceEnabled": false,  
      "bluetoothAlwaysPermission": "Allow BLE  
DEMO APP to connect to bluetooth devices"  
    }  
  ]  
]
```

To test anything Bluetooth-related, you'll **need a real device**. No simulator magic here — BLE just doesn't work in emulators.

Now, if you're using `npx expo run:android` or `npx expo run:ios`, make sure your device is physically connected (ADB for Android).

Alternatively, you can go the recommended route by creating a **custom development build** using EAS. This method gives you a permanent

dev client on your device you can reuse anytime.

First, update your `eas.json` to include the `developmentClient: true` flag:

```
{
  "cli": {
    "version": ">= 3.9.0"
  },
  "build": {
    "development": {
      "developmentClient": true,
      "distribution": "internal",
      "ios": {
        "resourceClass": "m-medium"
      },
      "channel": "development"
    }
  }
}
```


Then, run the build:

```
eas build --profile development --platform android
```

Once the build is installed on your device, you can simply start the dev server:

```
npx expo start
```

then scan the QR code to launch the app inside your custom client.

 Want to learn more? Check out the official Expo docs on [creating dev builds](#).

Basic UI Development

To keep our BLE demo clean and modular, I created a few reusable components that handle

both connection states and device lists.

Full source code here:

👉 [GitHub Repo](#)

We'll structure the UI using **three components** inside a folder named `components/bluetooth/`:

1. `ConnectedState.tsx` – When you're connected to a BLE device
2. `DisconnectedState.tsx` – When you're not connected (yet)
3. `PeripheralList.tsx` – To show scanned devices and connect to them

Let's take a peek into each one.

For the `components/bluetooth/ConnectedState.tsx` Component.

This component appears once a peripheral is successfully connected. It displays service info and lets you perform **READ**, **WRITE**, and **DISCONNECT** actions.

```
import { View, Text, TouchableOpacity, StyleSheet
} from "react-native";
import React from "react";
import { PeripheralServices } from
"@/types/bluetooth";

interface ConnectedStateProps {
  bleService: PeripheralServices;
  onRead: () => void;
  onWrite: () => void;
```

```

    onDisconnect: (id: string) =>
void;
}
const ConnectedState:
React.FunctionComponent<ConnectedSt
ateProps> =
({bleService,onDisconnect,onRead,on
Write}) => {
  return (
    <>
      <View style={styles.card}>
        <Text style={styles.info}>
          Peripheral ID:
{bleService.peripheralId} dBm
        </Text>
        <Text style=
{styles.info}>Service ID:
{bleService.serviceId}</Text>
      </View>
      <View style=
{styles.actionButtons}>
        <TouchableOpacity
          onPress={onRead}
          style={styles.button}
        >
          <Text style=
{styles.buttonText}>READ</Text>
        </TouchableOpacity>
        <TouchableOpacity
          onPress={onWrite}
          style={styles.button}
        >

```

```

        <Text style=
{styles.buttonText}>WRITE</Text>
        </TouchableOpacity>
        <TouchableOpacity
            onPress={() =>
onDisconnect(bleService.peripheralI
d)}
            style=
{styles.disconnectButton}
        >
            <Text style=
{styles.buttonText}>DISCONNECT</Tex
t>
            </TouchableOpacity>
        </View>
    </>
);
};
export default ConnectedState;
const styles = StyleSheet.create({
    actionButtons: {
        flexDirection: "row",
        marginTop: 16,
    },
    button: {
        backgroundColor: "#007AFF",
        padding: 12,
        borderRadius: 8,
        marginHorizontal: 8,
        flexGrow: 1,
    },
    disconnectButton: {

```

```

        backgroundColor: "red",
        padding: 12,
        borderRadius: 8,
        marginHorizontal: 8,
    },
    buttonText: {
        color: "#fff",
        fontSize: 16,
        textAlign: "center",
        fontWeight: "500",
    },
    info: {
        fontSize: 14,
        color: "#333",
    },
    card: {
        backgroundColor: "#fff",
        padding: 16,
        marginVertical: 8,
        borderRadius: 10,
        shadowColor: "#000",
        shadowOffset: { width: 0,
height: 2 },
        shadowOpacity: 0.1,
        shadowRadius: 4,
        elevation: 3,
    },
    });DisconnectedState.tsx

```

For the
components/bluetooth/PeripheralList
.tsx Component.

This is what users see when there's no connection. They can scan for peripherals and tap to connect.

```
import { StyleSheet, Text, TouchableOpacity } from
"react-native";
import React from "react";
import PeripheralList from "../PeripheralList";
import { StrippedPeripheral } from
"@/types/bluetooth";
```

```
interface DisconnectedStateProps {
  peripherals:
    StrippedPeripheral[];
  isScanning: boolean;
  onScanPress: () => void;
  onConnect: (peripheral:
    StrippedPeripheral) =>
    Promise<void>;
}
```

```
const DisconnectedState:
  React.FunctionComponent<Disconnecte
    dStateProps> = ({
    isScanning,
    onScanPress,
    peripherals,
    onConnect,
  }) => {
    return (
      <>
        <TouchableOpacity style=
          {styles.scanButton} onPress=
            {onScanPress}>
          <Text style=
```

```

{styles.scanButtonText}>
    {isScanning ?
"Scanning..." : "Start Scan"}
    </Text>
</TouchableOpacity>
    {peripherals.length > 0 ? (
        <PeripheralList onConnect=
{onConnect} peripherals=
{peripherals} />
        ) : (
            <Text style=
{styles.emptyText}>No peripherals
found</Text>
        )}
    </>
);
};
export default DisconnectedState;
const styles = StyleSheet.create({
    scanButton: {
        backgroundColor: "#007AFF",
        padding: 12,
        borderRadius: 8,
        marginBottom: 16,
    },
    scanButtonText: {
        color: "#fff",
        fontSize: 16,
        textAlign: "center",
        fontWeight: "500",
    },
    emptyText: {

```

```
        fontSize: 16,  
        color: "#666",  
        marginTop: 20,  
      },  
    ));
```

For the
components/bluetooth/PeripheralList
.tsx Component.

Get Chinweike Chinonso Michael's stories in your inbox

Join Medium for free to get updates from this writer.

This component handles the rendering of available BLE peripherals in a simple list.

```
import { StrippedPeripheral } from  
"@/types/bluetooth";  
import React from "react";  
import {  
  View,  
  FlatList,  
  StyleSheet,  
  Text,  
  TouchableOpacity,  
} from "react-native";  
  
interface PeripheralListProps {  
  peripherals:  
    StrippedPeripheral[];  
  onConnect: (peripheral:  
    StrippedPeripheral) =>  
    Promise<void>;  
}  
  
const PeripheralList:
```

```

React.FC<PeripheralListProps> = ({
  peripherals,
  onConnect,
}) => {
  return (
    <View style={styles.container}>
      <FlatList
        data={peripherals}
        keyExtractor={(item) =>
item.id}
        renderItem={({ item }) => (
          <TouchableOpacity
onPress={() => onConnect(item)}
style={styles.card}>
            <Text style=
{styles.title}>{item.name ??
"Unknown Device"}</Text>
            <Text style=
{styles.subtitle}>
              Local Name:
{item.localName ?? "N/A"}
            </Text>
            <Text style=
{styles.info}>RSSI: {item.rssi}
dBm</Text>
            <Text style=
{styles.info}>ID: {item.id}</Text>
          </TouchableOpacity>
        )}
      </>
    </View>
  );

```

```
};  
const styles = StyleSheet.create({  
  container: {  
    flex: 1,  
    // padding: 16,  
  },  
  card: {  
    backgroundColor: "#fff",  
    padding: 16,  
    marginVertical: 8,  
    borderRadius: 10,  
    shadowColor: "#000",  
    shadowOffset: { width: 0,  
height: 2 },  
    shadowOpacity: 0.1,  
    shadowRadius: 4,  
    elevation: 3,  
  },  
  title: {  
    fontSize: 18,  
    fontWeight: "bold",  
    marginBottom: 4,  
  },  
  subtitle: {  
    fontSize: 14,  
    color: "#555",  
    marginBottom: 4,  
  },  
  info: {  
    fontSize: 14,  
    color: "#333",  
  },  
});
```

```
});  
export default PeripheralList;
```

Now lets dive in to the implementation in our Home screen in the app/(tabs)/index.tsx folder

1. State Initialisation & Event Handlers

```
const [isScanning, setIsScanning] =  
useState(false);  
    const [peripherals, setPeripherals] = useState(  
        new Map<Peripheral["id"], Peripheral>()  
    );  
    const [isConnected, setIsConnected] =  
useState(false);  
    const [bleService, setBleService] =  
useState<PeripheralServices | undefined>(  
    undefined  
);  
  
useEffect(() => {  
    BleManager.start({ showAlert:  
false })  
        .then(() =>  
console.debug("BleManager  
started."))  
        .catch(console.error);  
    const listeners = [  
  
BleManager.onDiscoverPeripheral(handleDiscoverPeripheral),  
  
BleManager.onStopScan(handleStopScan),  
  
BleManager.onConnectPeripheral(handle
```

```

leConnectPeripheral),

BleManager.onDidUpdateValueForCharacteristic(handleUpdateValueForCharacteristic),

BleManager.onDisconnectPeripheral(handleDisconnectedPeripheral),
];
handleAndroidPermissions();
return () => listeners.forEach(l => l.remove());
}, []);

```

Initialises the BLE manager and declares your four key state variables (`isScanning`, `peripherals`, `isConnected`, `bleService`), wires up handlers for discovery, scan stop, connect, characteristic updates, and disconnect events, requests Android BLE permissions, and cleans up all listeners on unmount.

bleService (State) & PeripheralServices (Types)

We import this type from `types/bluetooth.ts`:

```

export type PeripheralServices = {
  peripheralId: string;
  serviceId: string;
  transfer: string;
  receive: string;
}

```

bleService just holds those four UUIDs (device ID, service UUID, write-char UUID, notify-char UUID) so you can safely pass them into your read/write/disconnect calls.

2. Scanning for Devices

startScan()

```
const startScan = async () => {
  const state = await BleManager.checkState();

  if (state === "off") {
    if (Platform.OS ===
"ios") {
      Alert.alert(
        "Enable Bluetooth",
        "Please enable
Bluetooth in Settings to
continue.",
        [
          { text: "Cancel",
style: "cancel" },
          { text: "Open
Settings", onPress: () =>
Linking.openURL("App-
Prefs:Bluetooth") },
        ]
      );
    } else {
      await
BleManager.enableBluetooth();
    }
  }
}
```



```

if (!isScanning) {
    setPeripherals(new Map());
    setIsScanning(true);
    BleManager.scan(
        SERVICE_UUIDS,
        SECONDS_TO_SCAN_FOR,
        ALLOW_DUPLICATES,
        {
            matchMode:
BleScanMatchMode.Sticky,
            scanMode:
BleScanMode.LowLatency,
            callbackType:
BleScanCallbackType.AllMatches,
        }
    );
}
};
}

```

1. Check & enable Bluetooth.
2. On **iOS**, apps **cannot** enable Bluetooth programmatically due to platform restrictions, so we redirect users to the Settings app. While on **Android**, you can toggle it in-app via `BleManager.enableBluetooth()`.
3. Reset your list and kick off a 5-second scan.
4. `ALLOW_DUPLICATES` ensures RSSI updates show up.

handleDiscoverPeripheral

```

const handleDiscoverPeripheral = (peripheral:
Peripheral) => {
    if (!peripheral.name) {
        peripheral.name = "NO NAME";
    }
}

```

```

        setPeripherals((map) => {
            return new Map(map.set(peripheral.id,
peripheral));
        });
    };
};

```

3. Connecting to a Peripheral

```

const connectPeripheral = async (
    peripheral: Omit<Peripheral, "advertising">
) => {
    try {
        if (peripheral) {
            setPeripherals((map) => {
                let p = map.get(peripheral.id);
                if (p) {
                    p.connecting = true;
                    return new Map(map.set(p.id, p));
                }
                return map;
            });
            await BleManager.connect(peripheral.id);
            console.debug(`[connectPeripheral]
[${peripheral.id}] connected.`);
            setPeripherals((map) => {
                let p = map.get(peripheral.id);
                if (p) {
                    p.connecting = false;
                    p.connected = true;
                    return new Map(map.set(p.id, p));
                }
                return map;
            });
            // give bonding time
            await sleep(900);
            /* Test read current RSSI value, retrieve
services first */
            const peripheralData = await
BleManager.retrieveServices(peripheral.id);
            if (peripheralData.characteristics) {
                const peripheralParameters = {
                    peripheralId: peripheral.id,
                    serviceId: DEVICE_SERVICE_UUID,
                    transfer:
TRANSFER_CHARACTERISTIC_UUID,

```

```

        receive: RECEIVE_CHARACTERISTIC_UUID,
      };
      setBleService(peripheralParameters);
      setIsConnected(true);
    }
    setPeripherals((map) => {
      let p = map.get(peripheral.id);
      if (p) {
        return new Map(map.set(p.id, p));
      }
      return map;
    });
  }
} catch (error) {
  console.error(
    `[connectPeripheral][${peripheral.id}]
connectPeripheral error`,
    error
  );
}
};

```

Key Points.

1. Connect by ID.
2. Wait ~900 ms for bonding.
3. Pull services/characteristics and stash your UUIDs in bleService.

Service & Characteristic UUIDs

You can hardcode these if your IoT device advertises them (as I did), or fetch them dynamically:

```

const data = await
BleManager.retrieveServices(peripheral.id);
console.log(data.characteristics);

```

4. Writing & Reading Data

write()

```
const write = async () => {
  const MTU = 255;
  if (bleService) {
    const data = Array.from(new
TextEncoder().encode("Hello World"));
    await BleManager.write(
      bleService.peripheralId,
      bleService.serviceId,
      bleService.transfer,
      data,
      MTU
    );
  }
};
```

What's going on here?

1. We use `TextEncoder` to convert "Hello World" into bytes—BLE deals with raw data, not plain text.
2. Then we call `BleManager.write()` to send it to the device.
3. The MTU (Maximum Transmission Unit) in Bytes tells the BLE stack how many bytes can be sent in one go—255 bytes works fine for short messages like this.

TextEncoder is available in most modern JS environments, but if you get an error saying it's undefined, just install the polyfill:

```
yarn add text-encoding
```

read()

```
const read = async () => {
  if (bleService) {
    const response = await BleManager.read(
      bleService.serviceId,
      bleService.peripheralId,
      bleService.receive
    );
    return response;
  }
};
```

```

    }
  };

```

5. Disconnecting

```

const disconnectPeripheral = async (peripheralId:
string) => {
    await BleManager.disconnect(peripheralId);
    setBleService(undefined);
    setPeripherals(new Map());
    setIsConnected(false);
};

```

Below is a nutshell of BluetoothDemoScreen code . Please Note the states, effects and logic hidden for clarity. [Clone the repo](#) for the full code and give it a spin.

```

const BluetoothDemoScreen: React.FC = () => {
  /* states, useeffect, logic here */
  return (
    <View style={styles.container}>
      <Text style={styles.header}>Bluetooth
Demo</Text>
      {!isConnected ? (
        <DisconnectedState
          peripherals=
{Array.from(peripherals.values())}
          isScanning={isScanning}
          onScanPress={startScan}
          onConnect={connectPeripheral}
        />
      ) : (
        bleService && (
          <ConnectedState
            bleService={bleService}
            onRead={read}
            onWrite={write}
            onDisconnect={disconnectPeripheral}
          />
        )
      )}
    </View>
  );

```

```
};  
/* UI style Sheet here*/  
export default BluetoothDemoScreen;
```

This article covers the core stuff to get you up and running. But yeah — there's a lot more you can do with `react-native-ble-manager` that I didn't touch here. Docs are linked below if you're curious.

Conclusion